


ANDROID: SET UP THE CLOUD WORKSPACE® CLIENT

This guide provides instructions for Android Users installing the Microsoft RDP client. Please note that you do not need to set up the Microsoft RDP client in order to access the Cloud Workspace via a HTML5 enabled browser – you would simply navigate to login.cloudjumper.com.


INSTALLING THE RDP CLIENT ON ANDROID DEVICES

The Microsoft RDP client is an easy, one-time install that will allow you to access the Cloud Workspace via RDP. Follow these simple instructions to download and install the Cloud Workspace RDP client.

- Open the Google Play store and search for **Microsoft Remote Desktop Client**, then download it
- Open the **Microsoft Remote Desktop Client** and tap **Remote Desktops** to continue




- Tap the + sign to continue






ANDROID: SET UP THE CLOUD WORKSPACE CLIENT

- Enter a name for your Remote Desktop connection (example: My Cloud Desktop)
- Enter the PC Name (aka Server Name) provided by nGenx, then tap **Gateway** to continue



- Select **Add Gateway** to continue





ANDROID: SET UP THE CLOUD WORKSPACE CLIENT

- Enter the Gateway Server name provided by CloudJumper
 - Name your Gateway if desired, but do not enter credentials here

3:00 PM

Edit Gateway

REMOTE DESKTOP GATEWAY

Gateway name
Friendly name for the gateway (optional)

Server
gw.nfinitycloud.com

Optionally append port information to the server name (RDGateway:443 or 10.0.0.1:443)

CREDENTIALS

User name
Domain\user

- Tap the check mark to continue
- Enter the User name and Password provided by CloudJumper and tap the check mark to continue

3:01 PM

Remote Desktop

name (MyDesktop:3389 or 10.0.0.1:3389)

Gateway
gw.nfinitycloud.com

CREDENTIALS

User name
user1@democlient1


Password
.....

User name
Domain\user


Password

ANDROID: SET UP THE CLOUD WORKSPACE CLIENT

- The connection to the Cloud Workspace is complete - tap the connection to launch the Cloud Workspace



- The Cloud Workspace will appear as it does below



The RDP client is now set up correctly. You will not need to do this again – this is a one-time install.